

WHERE IN THE WORLD IS CARMEN SANDIEGO?™

This special reference card shows you how to begin playing WHERE IN THE WORLD IS CARMEN SANDIEGO? on your Tandy Color Computer 3.

Carefully follow these step-by-step instructions to start up your computer and load this program:

- 1** Power up your Tandy Color Computer 3 as shown in the owner's manual.
- 2** Insert the WHERE IN THE WORLD IS CARMEN SANDIEGO? program disk into the disk drive; label side up (side A) and the oval cutout pointed toward the back of the system. Now close the drive door.
- 3** Type: DOS and press the ENTER key. This will boot up OS-9, your operating system.
- 4** You will then see a prompt asking for your monitor type. If you are using an analog RGB monitor (such as the Tandy CM-8) type R, otherwise type C.
- 5** Next the title screen will appear. Press ENTER to begin the game. If you have a joystick, press CTL-K to activate it.

Note: If your computer does not recognize the command "DOS," refer to the section below on starting from Disk Extended BASIC.



CONTROLS

Keys	Result
CTRL V	toggle video RGB/composite
CTRL K	toggle joystick/keyboard
CTRL S	toggle sound on/off
CTRL C	current rank
CTRL D	delete detective
CTRL F	display Hall of Fame
BREAK	abort any selected menu
CTRL R	restart game
CTRL Q	quit game

STARTING WHERE IN THE WORLD IS CARMEN SANDIEGO? FROM DISK EXTENDED BASIC

If you do not have a Color Computer with BASIC version 1.1 or later, or if you do not have the OS-9 System, you can type in the following Disk Extended BASIC program and use it to start WHERE IN THE WORLD IS CARMEN SANDIEGO?

Disk Extended BASIC is built right into your computer. After turning on your computer and with no disks in your disk drives, type:

```
10      REM      *****
20      REM      * BOOT OS-9 FROM BASIC
30      REM      *****
40      FOR I = 0 TO 70
```



```

50      READ A$
60      POKE  &H5000 + I,VAL("&H" + A$)
70      NEXT I
80      CLS: PRINT "INSERT 059 DISKETTE"
90      PRINT  "INTO DRIVE 0 AND PRESS A KEY"
100     A$ = INKEY$:IF A$ = ""THEN 100
110     EXEC  &H5000
120     DATA  86,22,8E,26,00,8D,0D
130     DATA  FC,26,00,10,83,4F,53
140     DATA  26,03,7E,26,02,39,34
150     DATA  20,10,8E,C0,06,A7,22
160     DATA  86,02,A7,A4,6F,21,6F
170     DATA  23,6C,23,AF,24,10,8E
180     DATA  C0,06,A6,23,81,13,27
190     DATA  12,AD,9F,C0,04,4D,27
200     DATA  06,6C,23,6C,24,20,E9
210     DATA  7F,FF,40,3S,A0,4F,20
220     DATA  F8

```

You should now save the above BASIC program so that you won't have to type it again. Insert a newly formatted disk into your disk drive and at the "OK" prompt type:

SAVE **"

and press **ENTER**

Then, to start the application using this Disk Extended BASIC program, type:

RUN **"

and press **ENTER**

When the next prompt appears, insert side A of the WHERE IN THE WORLD IS CARMEN SANDIEGO? disk into the disk drive and press **ENTER**.

STARTING UP YOUR COMPUTER WITH A SYSTEM DISK

If you started up your computer on a separate OS-9 system disk, put the Carmen disk in drive 0 and type:

CHX /D0/CMD5

Then, at the prompt, type:

CHD /D0

and at the next prompt type:

CARMEN

and press **ENTER** to start **WHERE IN THE WORLD IS CARMEN SANDIEGO?**

Note: If you have moved **WHERE IN THE WORLD IS CARMEN SANDIEGO?** to a double-sided disk, a hard disk or a RAM disk, you must provide additional directory information in order to start the program. The execution directory must indicate the location of the file "CARMEN." The data directory must indicate the location of all other files that come on the **WHERE IN THE WORLD IS CARMEN SANDIEGO?** disk.

For further information on this procedure please consult your OS-9 manual.

